

HASP 4.96 Driver Installation

For MAP Customers using EST-Duct / CAD-Duct Solids / CAM-Duct "PM2000"

Step 1 - Uninstall previous versions of the HASP driver

Please remove the dongle from the workstation

1. Download the 4.96 Drivers (Hinstall_496.ZIP) to your Desktop
2. Extract the content (**hinstall.exe, haspds_windows.dll & readme.txt**) to the following locations:

- 📁 **EST-Duct** - C:\EST-PMXTRA
- 📁 **CAM-Duct/PM2000** - C:\CAM\XTRA
- 📁 **CAD-Duct Solids** - C:\Program Files\CadDuct Solids

3. Click "Yes" if prompted to overwrite
4. Go to Start > Run
5. Click Browse
6. Browse to the location of the hinstall.exe
7. Highlight with one Left Click
8. Click Open

You should now be back to the Run dialogue with one of the following text strings present:

- **EST** - C:\EST-PMXTRA\hinstall.exe -r -kp -alldr
- **CAM** - C:\CAM\XTRA\hinstall.exe -r -kp -alldr
- **CAD** - "C:\Program Files\hinstall.exe" -r -kp -alldr

9. Add the remove switch indicated in red
10. Click OK to remove the drivers
11. Restart the machine

Step 2 – Install the HASP 4.96 driver version

1. Go to Start > Run
2. Select the previous text string from the drop down menu

- **EST** - C:\EST-PMXTRA\hinstall.exe -i
- **CAM** - C:\CAM\XTRA\hinstall.exe -i
- **CAD** - "C:\Program Files\CadDuct Solids\hinstall.exe" -i

3. Replace the remove switch with the install switch indicated in red
4. Click OK to install the drivers

The application should now work with the dongle.